SERENA®

DIMENSIONS® RM 2010 R1

Command Line Parameters Quick Reference

Serena Proprietary and Confidential Information

Copyright © 2001–2010 Serena Software, Inc. All rights reserved.

This document, as well as the software described in it, is furnished under license and may be used or copied only in accordance with the terms of such license. Except as permitted by such license, no part of this publication may be reproduced, photocopied, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, recording, or otherwise, without the prior written permission of Serena. Any reproduction of such software product user documentation, regardless of whether the documentation is reproduced in whole or in part, must be accompanied by this copyright statement in its entirety, without modification.

This document contains proprietary and confidential information, and no reproduction or dissemination of any information contained herein is allowed without the express permission of Serena Software.

The content of this document is furnished for informational use only, is subject to change without notice, and should not be construed as a commitment by Serena. Serena assumes no responsibility or liability for any errors or inaccuracies that may appear in this document.

Trademarks

Serena, TeamTrack, StarTool, PVCS, Collage, Comparex, Dimensions, RTM, Change Governance, and ChangeMan are registered trademarks of Serena Software, Inc. The Serena logo, Professional, Version Manager, Builder, Meritage, Command Center, Composer, Reviewer, Mariner, and Mover are trademarks of Serena Software, Inc.

All other products or company names are used for identification purposes only, and may be trademarks of their respective owners.

U.S. Government Rights

Any Software product acquired by Licensee under this Agreement for or on behalf of the U.S. Government, its agencies and instrumentalities is "commercial software" as defined by the FAR. Use, duplication, and disclosure by the U.S. Government is subject to the restrictions set forth in the license under which the Software was acquired. The manufacturer is Serena Software, Inc., 1900 Seaport Blvd., Redwood City, CA 94063.

Publication date: September 2010

Command Line Parameters

This guide contains Serena® Dimensions® RM command line parameters. The commands are organized by tool.

Tool	Action	Command
RM Concept	Create a new pending action.	`icconcept -action 16391 -pending -1 -user user -password password -location database -project project`
	Create a new collection.	`icconcept -action 16387 -user user -password password -location database -project project`
	Create a new form.	`icconcept -action 16385 -user user -password password -location database -project project`
	Create a new object.	`icconcept -action 16393 -user user -password password -location database -project project`
	Launch RM Concept.	`icconcept -user user -password password -location database -project project`
	Open pending action.	`icconcept -action 16391 -pending actionid -user user -password password -location database -project project`
	Open class with default form.	`icconcept -action 16384 -class classid -form -1 -list 0 -user user -password password -location database -project project`
	Open class with specific form.	`icconcept -action 16384 -class classid -form formid -list 0 -user user -password password -location database -project project`
	Open class with specific grid layout.	`icconcept -action 16384 -class classid -form -1 -list 1 -layoutid layoutid -user user -password password -location database -project project`
	Open class with default grid layout.	`icconcept -action 16384 -class classid -form -1 -list 1 -user user -password password -location database -project project`
	Open class form.	`icconcept -action 16384 -class classid -form formid -list 0 -user user -password password -location database -project project`
	Open class form in layout mode.	`icconcept -action 16386 -class classid -form formid -user user -password password -location database -project project`
	Open relationship form.	`icconcept -action 16392 -rel relationshipid -form formid -user user -password password -location database -project project`
	Open collection.	`icconcept -action 16388 -keyword collectionname -user user -password password -location database -project project`
	Open relationship with default form.	`icconcept -action 16392 -rel relationshipid -form -1 -user user -password password -location database -project project`

Tool	Action	Command
RM Concept (cont'd)	Open relationship with specific form.	`icconcept -action 16392 -rel relationshipid -form formid -user user -password password -location database -project project`
	Run script (passing actual script text).	`icconcept -action 16390 -scriptflag 1 -scripttitle title -script script -run 1 -user user -password password -location database -project project`
	Open relationship object in default form.	`icconcept -action 16392 -rel relationshipid -form -1 -primary primaryid -secondary secondaryid -user user -password password -location database -project project`
	Run script (passing script name).	`icconcept -action 16390 -scriptflag 0 -script scriptname -run 1 -user user -password password -location database -project project`
	Open class object in default form.	`icconcept -action 16389 -object objectid -class classid -version version -user user -password password -location database -project project`
RM Capture	Launch RM Capture.	`capturetool -user user -password password -location database -project project`
	Open document in RM Capture.	`capturetool -documentid documentid -user user -password password -location database -project project`
RM Word	Launch RM Word.	`rtmword -user user -password password -location database -project project`
	Open document in RM Word.	`rtmword -documentid documentid -user user -password password -location database -project project`
	Open object in RM Word.	`rtmword -documentid documentid -classid classid -objectid objectid -user user -password password -location database -project project`
RM Manage	Launch RM Manage.	`icmanage -user user -password password -location database -project project -buffer buffer -dumpfile dumpfile`
Class Definition	Launch class definition.	`clasdef -user user -password password -location database -project project`
VNT	Launch collection in VNT.	`vnt -datasource database -objectid collectionid -user user -password password -location database -project project`
	Open object in VNT.	`vnt -datasource database -objectid objectid -classid classid -user user -password password -location database -project project`