

SERENA® DIMENSIONS® CM 14.3.2

Docker Registry Guide

Serena Proprietary and Confidential Information

Copyright © 2014–2016 Serena Software, Inc. All rights reserved.

This document, as well as the software described in it, is furnished under license and may be used or copied only in accordance with the terms of such license. Except as permitted by such license, no part of this publication may be reproduced, photocopied, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, recording, or otherwise, without the prior written permission of Serena. Any reproduction of such software product user documentation, regardless of whether the documentation is reproduced in whole or in part, must be accompanied by this copyright statement in its entirety, without modification.

This document contains proprietary and confidential information, and no reproduction or dissemination of any information contained herein is allowed without the express permission of Serena Software.

The content of this document is furnished for informational use only, is subject to change without notice, and should not be construed as a commitment by Serena. Serena assumes no responsibility or liability for any errors or inaccuracies that may appear in this document.

Trademarks

Serena, TeamTrack, StarTool, PVCS, Comparex, Dimensions, Prototype Composer, Mariner, and ChangeMan are registered trademarks of Serena Software, Inc. The Serena logo and Version Manager are trademarks of Serena Software, Inc. All other products or company names are used for identification purposes only, and may be trademarks of their respective owners.

U.S. Government Rights

Any Software product acquired by Licensee under this Agreement for or on behalf of the U.S. Government, its agencies and instrumentalities is "commercial software" as defined by the FAR. Use, duplication, and disclosure by the U.S. Government is subject to the restrictions set forth in the license under which the Software was acquired. The manufacturer is Serena Software, Inc., 2345 NW Amberbrook Drive, Suite 200, Hillsboro, OR 97006.

Publication date: October 2016

Table of Contents

Introduction	5
What is Docker?	6
Dimensions CM Integration with Docker	7
Installing and Licensing	8
Starting Docker	9
Starting a Docker Registry	10
Using a Docker Registry without SSL	12
Protecting a Docker Registry with SSL	13
Creating a Certificate Authority	13
Generating Certificates and Keys	13
Trusting a Certificate Authority	14
Configuring Docker to Trust a Registry	14
Creating a Keystore	15
Starting a Docker Registry in SSL Mode	15
Logging in Securely to a Remote Docker Registry	15
Using Docker	17
Creating a Docker Image	18
	18
Pushing an Image	18
Approving an Image	19
Searching for Images	19
Pulling an Image	20
Specifying Change Requests	20
Using the Example Docker Image	21
	22
	22
	22
-	22
Supported Parameters	22 23
	Dimensions CM Integration with Docker Installing and Licensing Starting Docker Starting a Docker Registry Using a Docker Registry without SSL Protecting a Docker Registry with SSL Creating a Certificate Authority Generating Certificates and Keys. Trusting a Certificate Authority Configuring Docker to Trust a Registry. Creating a Keystore. Starting a Docker Registry in SSL Mode Logging in Securely to a Remote Docker Registry Using Docker. Creating a Docker Image Logging into a Dimensions CM Docker Registry Pushing an Image Approving an Image. Searching for Images. Pulling an Image

Serena® L	Dimensions [®]	СМ
-----------	-------------------------	----

Chapter 1

Introduction


What is Docker?	6
Dimensions CM Integration with Docker	7
Installing and Licensing	8

What is Docker?

Docker enables you to create lightweight environments, called *containers*, in which you can run applications (Docker images). Containers run as isolated processes on a host operating system and are not tied to any specific infrastructure. Docker runs on any machine, on any infrastructure, and on any cloud. Images are stored in a Docker Registry.

An image's environment, such as an application and the dependencies required to run it, are stored in layers. Containers share the host operating system kernel with other containers. Containers start and stop instantly and make more efficient use of RAM. You can run multiple containers of the same image.

In the example below there are two containers, each running the same application server image comprised of two layers, Tomcat and Centos. The containers are running on the same Docker Engine and share the host operating system.



Docker is a commercial company, for information see this web site:

https://www.docker.com/what-docker


Dimensions CM Integration with Docker

The Dimensions CM integration provides a Docker Private Registry for your images and has the following key features.

- Stores and version controls images. Changes to images over time are recorded so that you can recall specific versions later.
- Provides an audit trail of all changes to each image.
- Uses CM privileges and roles assignments to control which images can be pulled (downloaded). An image is only visible to the user who created it but is available to other users after it has been approved. For details about privileges, roles assignments, and relationships see the Process Configuration Guide.
- Enables change control of Docker images using Dimensions CM requests.

Dimensions CM Docker Registry images are stored in a secure CM repository:

- Each time an image is pushed (delivered) to CM a new baseline is created.
- Each image is a new design part.
- Each layer in an image is a new item with a unique filename.
- Layers can be shared between images using CM's usage relationships.



Installing and Licensing

The integration with Docker is installed and licensed separately from Dimensions CM. For details contact Serena Software.

Chapter 2

Starting Docker

Starting a Docker Registry	10
Using a Docker Registry without SSL	12
Protecting a Docker Registry with SSL	13

Starting a Docker Registry

NOTE If you are using Docker version 10, login to the registry using the Docker login command before performing any other registry operations.

To start a Dimensions CM Docker Registry run this command (parameters in square brackets are optional):

```
java -jar docker-registry.jar
--port=<port number>
--cm-url=scm:dimensions://<cm server>/<database>
--cm-product=<product>
--cm-stream=<product>:<stream>
--cm-part="<product>:<design part>"
[--cm-part-type=<type>]
[--cm-baseline-type=<type>]
[--cm-baseline-state=<state>]
[--work=<path>]
[--log-file=<path>]
[--manage-path=<path>]
[--manage-user=<user>]
[--manage-password=<password>]
[--ssl=false]
```

where:

port=<port number>

Specifies the port number of a Docker Registry.

Default: 5000

cm-url=scm:dimensions://<cm server>/<database>

Specifies a CM server and database, for example:

```
cm-url=scm:dimensions://mycmserver/cm_typical@dim14
```

cm-product=croduct>

Specifies a CM product for Docker Registry images, for example:

```
cm-product=QLARIUS
```

cm-stream=cm-stream>

Specifies a CM stream where new images are delivered, for example:

```
cm-stream=QLARIUS:DOCKER STREAM
```

cm-part="roduct>:<design part>"

Specifies a design part that will own pushed images, for example:

```
cm-part="QLARIUS:DOCKER IMAGES.A;1"
```

■ cm-part-type

Specifies the design part type for pushed images. Default: SUB-SYSTEM

■ cm-baseline-type=<type>

Each time an image is pushed (delivered) to CM a new baseline is created. Use this parameter to specify a type, for example:

cm-baseline-type=MYTYPE

Default: BASELINE

cm-baseline-state=<state>

Specifies the 'approved' state for baselines. Only images in 'approved' baselines can be searched and pulled. For example:

cm-baseline-state=APPROVED

Default: APPROVED

■ work=<path>

By default Dimensions CM Docker Registry uses C:\ProgramData\Docker_work to store temporary files when images are pushed and pulled. Use this parameter to specify a different location, for example:

work=/tmp/docker-registry

■ log-file=<path>

By default Dimensions CM Docker Registry uses C:\ProgramData\Serena\Docker_logs\docker-registry.log to store log files. Use this parameter to specify a different location, for example:

log-file=/tmp/Serena/Docker/_logs/docker-registry.log

manage-path=<path>

manage-user=<user>

manage-password=<password>

By default Dimensions CM Docker Registry uses /system as the prefix for all diagnostic endpoints. The default user is admin and the default password is secret. You can specify your own path prefix and security credentials, for example:

manage-path=/manager
manage-user=superuser
manage-password=password

ssl=false

Starts Dimensions CM Docker Registry without Secure Socket Layer (SSL) protection.

specifies the "type" of design part to create when a docker image is pushed into the registry. The default value for the parameter is "SUB-SYSTEM".

Using a Docker Registry without SSL

Docker prefers registries to be protected with SSL. If you have a non-SSL registry you must tell Docker to make an exception and allow access.

1 Use Secure Shell (SSH) to log into the system running your Docker Engine. If you are using the Docker Toolbox on Windows this is a Virtual Image running under VirtualBox. You will need the IP address of that system to SSH into it. On Linux, SSH into the Linux system itself. If you are using the boot2docker image you can login as:

Username: docker Password: tcuser

2 Edit the Docker profile and specify that the registry is insecure:

cd /var/lib/boot2docker
sudo sh
vi profile

At the top of this file EXTRA_ARGS is defined. Add this line:

--insecure-registry=myregistryserver:5000

- **3** Change the host name and port number as needed and save the file.
- 4 Restart Docker:

/etc/init.d/docker restart

5 Log into a Dimensions CM Docker Registry:

docker login <myregistryserver>:<port number>

6 Enter Dimensions CM login credentials. If the login is successful you have configured Docker to use the non-SSL registry.

Protecting a Docker Registry with SSL

This section is an example of how to SSL protect a Dimensions CM Docker Registry using a self-signed certificate.

Creating a Certificate Authority

- 1 Use SSH to log into the boot2docker image (or the Linux system) that hosts your Docker engine.
- **2** Run sudo sh to change to a root shell.
- **3** Generate a Certificate Authority (CA) certificate and key pair (you can optionally change the password and subject):

```
cd /usr
mkdir ca_certs
chmod 700 ca_certs
cd ca_certs
mkdir certs private newcerts
echo 1000 > serial
touch index.txt
openssl req -new -x509 -days 3650 -extensions v3_ca \
    -keyout private/cakey.pem -out cacert.pem \
    -config /etc/ssl/openssl.cnf -passout pass:passwordformyca -subj \
    "/C=UK/ST=Surrey/L=Richmond/O=Acme/OU=Development/CN=Acme"
```

Generating Certificates and Keys

Generate a certificate/key pair for the machine that will run your Dimensions CM Docker Registry and sign it with the CA you created in the previous step.

- 1 Use SSH to log into the boot2docker image (or any system where you are running the Docker Engine).
- 2 Run sudo sh
- **3** Run:

```
cd /usr
mkdir certs
openssl genrsa -out /usr/certs/domain.key 2048
openssl req -new -key /usr/certs/domain.key -out /usr/certs/ \
   domain. csr -subj "/C=UK/ST=Surrey/L=Richmond \
    /0=Acme/OU=Development/CN=<host running Docker Registry>"
openssl x509 -req -days 365 -in /usr/certs/domain.csr -signkey \
    /usr/certs/domain.key -out /usr/certs/domain.crt -CAkey /usr \
    ca_certs/private/cakey.pem -CA /usr/ca_certs/cacert.pem \
    -CAcreateserial -CAserial /usr/ca_certs/serial
```

where:

- /usr/ca_certs/private/cakey.pem
 Is the private key for the CA.
- /usr/ca_certs/cacert.pem
 Is the public certificate for the CA.
- /usr/certs/domain.key
 Is the private key for the registry server.
- /usr/certs/domain.crt
 Is the public certificate for the registry server.

Trusting a Certificate Authority

Next you need to tell the Linux operating system inside the boot2docker image to trust the generated CA certificate. Usually Linux has scripts to do this but they are missing from the boot2docker Linux distribution so you need to do it manually.

Replace 4c05dafl with whatever hash is returned by the openssl x509 hash command:

```
cp /usr/ca_certs/cacert.pem /usr/local/share/ca-certificates/yourca.pem
cd /etc/ssl/certs
ln -s /usr/local/share/ca-certificates/yourca.pem
openssl x509 -hash -in serenaca.pem
ln -s serenaca.pem 4c05dafl
```

Configuring Docker to Trust a Registry

Every Docker Engine machine from which you want to access a remote Docker Registry requires a directory that matches your registry URL. Add your CA certificate and restart docker.

- **1** Use SSH to log into the boot2docker image on each remote host.
- **2** Run:

```
mkdir -p /etc/docker/certs.d/myregistryserver:5000
cd /etc/docker/certs.d/myregistryserver:5000
```

- 3 Create a file called ca.crt containing the contents of the CA public certificate in: /usr/ca_cert/cacert.pem
- 4 Restart Docker:

```
/etc/init.d/docker restart
```

Creating a Keystore

1 Create a PKCS12 keystore that the Dimensions CM Docker Registry can use to identify itself:

```
openssl pkcs12 -export -in /usr/certs/domain.crt -inkey /usr/ \
  certs/domain.key out /usr/certs/keystore.p12 -name \
  tomcat -CAfile /usr/ca certs/cacert.pem -caname root -chain
```

2 Copy the generated keystore.p12 file to the system running the Docker CM Registry JAR.

Starting a Docker Registry in SSL Mode

Now that you have a SSL keystore, specify that it can be used when you start a Dimensions CM Docker Registry:

```
java -jar docker-registry.jar --port=5000 --ssl=true \
    --keystore=C:\temp\keystore.p12 \
    --keystore-type=PKCS12 \
    --keystore-pass=changeit \
    --cm-url=scm:dimensions://mycmserver/cm_typical@dim14 \
    --cm-product=QLARIUS --cm-stream=QLARIUS:DOCKER_STREAM \
    --cm-part=QLARIUS:DOCKER IMAGES.A;1
```

Use the keystore password that you entered when you created the keystore.

Logging in Securely to a Remote Docker Registry

Login securely to the remote Docker Registry:

```
docker login myregistryserver:5000
```

If the login is successful you have secured your Dimensions CM Docker Registry using SSL.

Chapter 3

Using Docker

Creating a Docker Image	18
Logging into a Dimensions CM Docker Registry	18
Pushing an Image	18
Approving an Image	19
Searching for Images	19
Pulling an Image	20
Specifying Change Requests	20

Creating a Docker Image

To create a Docker image:

```
docker build -t <image name> .
```

This is an example of how to build an image. Using Dimensions CM Docker Registry does not affect how you create images.

You can optionally add a tag to identify an image:

```
docker build -t <image name>:<tag name> .
For example:
docker build -t myimage:turnover .
```

Logging into a Dimensions CM Docker Registry

1 Run this command and specify the CM host machine and port number:

```
docker login <registry server>:<port>
For example:
docker login myregistryserver:5000
```

2 Enter credentials to log into CM.

Pushing an Image

```
To push (deliver) an image to a Dimensions CM Docker Registry:
```

```
docker push <registry server>:<port>/<image name>:<tag>
```

For example:

docker push myregistryserver:5000/insurancesvc:turnover

NOTE

- Docker image layers are delivered as items at the top of the stream (if they do not already exist).
- The item type and format used are determined by the CM upload rules. Check that you have an upload rule to handle files with no file extension.
- A new CM design part called <image name> is created, for example: INSURANCESVC

 The new part is created in a *product* and owned by a *parent design part*. The product and design part are configured by your administrator when the Docker Registry is started, see page 10.
- The manifest of the image is created as an item owned by that design part.

A new baseline is created from that design part containing the layers used by the image and the image manifest file:

```
<image name>-<tag>-<version>
```

For example:

INSURANCESVC-TURNOVER-1

- To save space in your repository, after you push an image:
 - Any layer that is no longer required is automatically deleted.
 - Only baselines that are at the *Approved* lifecycle state are preserved. All other baselines of the image are deleted.

Approving an Image

Images are only visible to the user who created them. To make an image visible to all users:

- **1** Log into a CM client as the owner of the baseline associated with the image.
- 2 Action the baseline to the Approved lifecycle state (this state was configured when the Docker Registry started, see page 10).

NOTE

- By default all images require approval though this can be switched off by a CM administrator when a Docker Registry is started.
- After an image is approved all users can search for and pull it, providing they have the required Dimensions CM privileges and roles.

Searching for Images

To list all images:

docker search <registry server>:5000/

Example output:

NAME DESCRIPTION

hello-world latest hello world image

insurancesvc Docker image ubuntu Some Ubuntu image

This is a list of all the images that you created or approved.

To search for images using a keyword:

docker search <registry server>:5000/ubun

Example output:

NAME DESCRIPTION

ubuntu Some Ubuntu image

Pulling an Image

To pull a specific image tag:

docker pull <registry server>:5000/<image>:<tag>

For example:

docker pull myregistryserver:5000/insurancesvc:turnover

The pull command downloads the image from the corresponding baseline. All Dimensions CM privileges and roles are honored by the pull request.

Specifying Change Requests

When you build or modify a Docker image you can specify Dimensions CM change requests using a LABEL called com.serena.requests inside your Docker file. For example if the Docker file contains:

```
FROM tomcat:8-jre8
LABEL com.serena.requests="QLARIUS_CR_21,QLARIUS_CR_25"
CMD ["catalina.sh", "run"]
```

when the image is pushed to the Dimensions CM Docker Registry, the resulting baseline is related to requests QLARIUS_CR_21 and QLARIUS_CR_25.

Chapter 4

Using the Example Docker Image

Overview	22
Building the Example Image	22
Running the Example Image	22

Overview

An example Docker image file is included with the Dimensions CM server installation and is placed in the same folder as the JAR file. The image is based on Alpine Linux (a compact Linux distribution ideal for containers) and includes:

- Oracle Java JDK 8
- The Dimensions CM Docker Registry JAR file
- A shell script to launch the registry

Building the Example Image

To build the image go to the directory containing the Docker file and run Docker build, for example:

```
docker build -t cmregistry .
```

Running the Example Image

Supported Parameters

The command line parameters for the Dimensions CM Docker Registry are passed to the image as environment variables. The supported parameters are:

```
docker run -it
    -e CM_URL=scm:dimensions://<server>/<base database>@<db connection>
    -e CM_PRODUCT=<product id>
    -e CM_STREAM=<product id>:<stream id>
    -e CM_PART=<full part specification>
    [-e CM_PART_TYPE=<part type name>]
    [-e CM_BASELINE_TYPE=<baseline type name>]
    [-e CM_BASELINE_STATE=<approval state name>]
    -p <port number>:5000
    cmregistry
```

The registry always listens on port 5000. However, you can map this to a different port when running the image. For example, to listen on port 5555 specify the following:

```
-p 5555:5000
```

For an SSL protected registry you can also specify:

```
-e SSL=true
-e KEYSTORE=<path to PKCS12 keystore file>
-e KEYSTORE_PASS=<password for your keystore>
```

NOTE You may also need to mount a volume containing your keystore file:

```
-v /c/Users/myuser/certs:/certs
```

Mandatory Parameters

You can run the registry with only the mandatory parameters, for example:

```
docker run -it
   -e CM_URL=scm:dimensions://mycmserver/cm_typical@dim14 \
   -e CM_PRODUCT=QLARIUS \
   -e CM_STREAM=QLARIUS:DOCKER_IMAGES \
   -e CM_PART="QLARIUS:DOCKER_IMAGES.A;1" \
   -p 5000:5000 \
   cmregistry
```

Running the Image in SSL Mode

To run the image in Secure Socket Layer (SSL) mode, specify the SSL, KEYSTORE, and KEYSTORE PASS environment variables. For example:

```
docker run -it -v /c/Users/myuser/certs:/certs \
    -e CM_URL=scm:dimensions://mycmserver/cm_typical@dim14 \
    -e CM_PRODUCT=QLARIUS \
    -e CM_STREAM=QLARIUS:DOCKER_IMAGES \
    -e CM_PART="QLARIUS:DOCKER_IMAGES.A;1" \
    -e SSL=true \
    -e KEYSTORE=/certs/mykeystore.p12 \
    -e KEYSTORE_PASS=changeit \
    -p 5000:5000 \
    cmregistry
```

NOTE For SSL mode mount a volume containing your keystore to the /certs mount point using the -v option. In the example above /c/Users/myuser/certs is mounted to /certs inside the container. That directory contains the mykeystore.p12 file containing certificates for the machine running the Docker engine.

Once the container is running, use it in the same way as when running the Dimensions CM Docker Registry JAR file. For details see page 17.